

- 1, Using [administrator privileges](#) to run “WinusbCopy.exe”;
- 2, if cmd window display “Repair the driver files success! Please re install the driver! ” Please Re-drive;
- 3, if cmd window display “Repair the driver files failed Error=5”. Please make sure you using the [administrator privileges](#),when run “WinusbCopy.exe”;
- 4, if cmd window display “Repair the driver files failed Error=*(* not is 5)”. Please try to manually repair.
Determine "C:\windows\system32\drivers\winusb.sys" file exists, Otherwise, serach winusb.sys in the "C:\windows",copy to "C:\windows\system32\drivers\".
Re-drive
- 5, If you can not solve, please contact us.

Contact Us:

Official Website: <http://www.instrustar.com/>

Telephone / Fax: +86-0451-57668072

Email: yixingdianzi@hotmail.com