

HH400_USB COM Port support!


Scan the following configuration bar code in order to enable the USB COM Port.

(3) USB Serial




USB Serial Interface


The Windows os is detecting a new hardware and tries to install a driver but fails.



Go to the Device Manager and search for the HH400.




Right Mouse click on the HH400 > Update Driver Software.....




Search for the driver where it is saved locally > HH400Vcom_Driver_170113 > click on install.


There is a Windows Security Warning > click on 'Install this driver software anyway'.



The System is updating the driver, which will take a few seconds!



After the successful installation of the USB COM Port driver following information is seen:



Check the Device Manager for the assigned COM Port!

